

How to register a Topocad 15 license on a server and how to connect client computers

Register on server

To register/run a Topocad 15 network license, the latest license server 5.1 is required. The license managing for Topocad has been restructured and Topocad is now verified in a new License Browser.

The new license browser on the server is called Licensebrowser32 and is located at:
C: \ Program Files (x86) \ Common Files \ Adtollo \ License Manager \ LicenseBrowser32.exe

NOTE! To run the new license server, previous license servers need to be uninstalled. Because of this, older licenses also need to be added and verified in the new Licensebrowser32.

1. Start the Licensebrowser32 by right-clicking the icon in the Windows Start menu or in Windows Explorer at C: \ Program Files (x86) \ Common Files \ Adtollo \ License Manager \ LicenseBrowser32.exe. Select "Run as administrator" from the right-click menu. This will launch the new License Browser.
2. Press the *Add* button in the License Browser and select *Topocad* and *Version 15*. A yellow key will appear with a 0 license number under *Applications*.
3. Highlight the license number with the yellow key and enter your license number at the top of the right column.
4. Press the *Register* button, select *Register online* and enter your registration key when requested.

Repeat the procedure for older versions/licenses.
When you're done, please restart the service/services "Adtollo license server".

Connect client computers

The current License browser on the client computers still handles Topocad version 14 and earlier. Topocad 15 requires a new License Browser.

The new browsers are called Licensebrowser32 and Licensebrowser64, and the selection depends on which operating system you have. Licensebrowser32 is used on 32-bit Windows and Licensebrowser64 is used on 64-bit Windows.

- Run the following Licensebrowser32 if you have a 32-bit Windows: C: \ Program Files \ Common Files \ Adtollo \ License Manager \ LicenseBrowser32.exe
- Run the following Licensebrowser64 if you have a 64-bit Windows: C: \ Program Files \ Common Files \ Adtollo \ License Manager \ LicenseBrowser64.exe

Follow the steps above to add the Topocad 15 licenses. Unlike the server – the licenses shall not be registered on the clients. However, the server name or address shall be entered under the *Settings* button.

After the procedure you are able to start Topocad on the clients.